How to activate HUA Dongle for Infinity Box/Dongle

- 1. Connect Infinit Box/Dongle to PC
- 2. Run Infinity "DongleManager" version 1.56 of higher !
- 3. Select your Box/Dongle type
- 4. Make "Read dongle serial number (S/N)" operation Instruction with images is **Here**
- 5. Send Serial Number (S/N) to your Reseller or use <u>Infinity Online Service</u>
 Do not send to Reseller Username/Password that you will see during S/N read procedure !
- 6. Wait a confirmation from Reseller If you use **Infinity Online Service** you will get an **instant** confirmation.
- 7. Run Infinity "DongleManager" once again and update your Box/Dongle firmware:
 - connect box to PC
 - click to "Upgrade dongle firmware" button
 - click to "Next" button
 - click to "Next" button
 - wait 1 minute until process finished
- 8. Read Serial Number (S/N) and be sure that you have new software activated

You must use HUA Dongle (All-in-One) Rev 1.3.4 or newer !

- 1. Download and install HUA Dongle software
- 2. Run Hua Dongle software
- 3. Select Infinity-Box and click to "Run" button



4. Wait some time, software will detect Dongle



5. Select **Option #4** and click to "**Ok**" button

👌 HUA Dongle	×		
If You See This Form it Because of these Reasons :			
1) Software Can't Found License File			
2) Maybe License File Was Curropted			
3) You Are New User and You Dont Have License File			
4) You Are Infinity Box User and You Dont Mave License File			
5) You Are Infinity Box User and You Update Your Card Recently from Dongle Manager			
- If You Are Using This Software Before and You Just Lost Your License File			
Please Select Option 1			
- If You Are Using This Software Before and Have License File			
Please Select Option 2			
- If You Are New User			
Please Select Option 3			
- If You Are Infinity Box User			
Please Select Option 4			
Then Press OK Button			
Your Card SN : coccosteres			
Your Infinity Card SN : CTANADA			
Options			
C1 C2 C3 04			

6. Enter your registration data and click to "**Request License**" button:

HUA Dongle Activator for Infinity Box User rev 1.0.0				
Registration	Form	Log		
First Name :	Michael	*	A	
Last Name :	Schumacher	*		
Email :	m.s@example.com	*		
Wechat :				
Whatsapp :				
Sonork :				
* Mandati	ory Field Must Be Filled			
	Request License			
	Recover License		•	

7. Wait little bit, software will get license from server

Disable your PC Firewall and/or Antivirus for best result !

Registration	LUg		
First Name : Michael Last Name : Schumacher Email : m.s@example.com Wechat : Whatsapp : Sonork : Mandatory Field Must Be Filled Request License Bacquar License	 Step 1 Step 2 Sendin Waiting Infinity Setting Activat Now Cl Discont 	Collecting Registration Data OK Retriving Card Information OK Connecting to Activation Server OK Register Request OK for Answer OK Sox SN : Control Control Activated! Card DataOK ion File Saved in C:\AHT\Control Control LIC ose software and Run it again hect from Server OK	

8. Restart **Hua Dongle** software, you will see your **Hua Dongle S/N**:

HUA Tool (Activated for Infinity Box) Rev 1.3.4				
Support				
Phone Type / Port / BaudRate / Boot Mode Setting	-Log Window			
Phone Type Select Port BaudRate Boot Mode SMART PHONE USB R 115200 ADB Mode *	HUA Dongle Rev 1.3.4			
Unlock IMEI Qualcomm Android LG	Contact Info: Support Department: Sonork: 100.1587178 Yahoo: doctor_asangsm@yahoo.com Official Sale for Iranian User's Store: http://www.asansamplus.com/shop/home-bannerize/hua-dongle-activation-on For More Info Visit www.huadongle.ir			
S/N: IIII Idle.	S.Shot STOP			